


Smart Blinds mobile app instruction












Press to add a blinds.




Select the roller shutter from the list (if you have several motors, we recommend turning on the next motor after adding the previous roller blind to the application).











The settings screen will appear.




You can find settings in the upper right corner of the application.












1. The name of the blind Give the roller **your** own name and **confirm**.




2. Type of blindChoose roller blind picture that suits you and **save**.




3. Change the passwordChange the password to your own and **confirm**.




4. Blind direction setting It is possible to change the direction of blind: to do this, press



blind Hold Open or Close until the blinds is fully open, press Stop and Save.



the blind Hold Open or Close until the blinds is closed completely, press Stop and Save.




Moving speed setting
The default is the fastest
winding speed. To decrease it,
press

For advanced users: enter the

<u>For advanced users:</u> enter the height of the roller blind and the diameter of the mechanism to adjust the winding time to your preferences.








8. Dot/Continuous setting

This setting determines whether or not each touch of **Open** and Close will cause the roller shutter to move, or it will be necessary to briefly hold it.




9. Winter / Summer mode

This setting is related to the light sensor in the solar panel *: if you don't have one, you don't have to do anything.



10. Timing settings allow you to set the opening or closing time of blind.


Press to start




10. Timing settings

Set the position of the blind moving the button

Select the exact time and press duplicate to select days.



10. Timing settings Select days and confirm.



To start the timer, press:



10. Timing settings

To edit or delete a timer hold your finger on its name longer.




10. Timing settings

You can set a maximum of 4 different timers.

To edit / delete, press and hold your finger longer on the timer.






11. Delete the blind

This setting is used to remove the blind from the app.




12. Clear all settings

You can delete all settings. This will restore the initial default settings.



Device control

The start screen of the application shows a list of all added blinds. Smart Blinds within bluetooth range will connect automatically after 2 to 3 seconds. Select the blind to control it.



Device control

You can control the roller shutter using buttons

Open - Stop - Close,
or by moving your finger on the drawing of the roller blind.

This screen also shows the battery level of the Smart Blinds device.



Scene control

Smart Blinds devices can be combined into groups to perform planned scenarios, e.g. to open all blinds in a room with one button.

To add first scene press






Scene control


Press scene name to add your name of scene. Then press to add chosen blinds.

(note: to add a roller blind, it must have the "connected" status in the application).



Scene device position

Set the desired roller blinds target position and press **Confirm.**



Scene device list

After adding the chosen blinds, press **save scene**.






Press the name of the selected group, and then the **start scene** button - the blind will move to the preset positions.



Scene control

Press and **hold** scene name to edit or delete a scene



Device control

Press device control to go back to start screen..

The manual applies to Smart Blinds version 1.0 (from 04/12/2020).

In the future, there may be new versions of the application introducing additional possibilities and functions.

Find information on this subject on the smartblinds.pl website or directly in the application store (Google Play or Apple APP Store).